
How to do software upgrade (AV-1560/1070 series)


• Connect the camera to your PC via an Ethernet cable, access the camera using IE browser (please refer to "How to access AViPAS camera via IP").



• Go to "upgrade v2.8" -> "upgrade.exe":



- Click on "Open", choose the ".img" file, for instance: AV-1070 uses "V70S_G3.V_V7.2.40_24M_20190108.img". Then click "Upgrade". The camera will reboot twice during the upgrade.
 - You'll find the download links for firmware files on the product page. If the firmware version is not listed, please send your request to service@avipas.com



• After the "Upgrade Success" message, click on "OK". Upgrade is done. Click on "Query" again, you'll see the updated Version Information (IP address and MAC address remain the same after upgrade). You may re-log into the web interface.

